



Knitted Bib

No. 2003-171-8082

Materials:

1 ball soft, Go Handmade col. 26
Circular needle size 3,5 mm / US 4, 60 cm
Crochet hook size 2,5 mm
1 wooden button size 15 mm

Gauge:

23 stitches per 10 cm
30 rows per 10 cm

Purchase the yarn here:

<http://shop.hobbii.com/knitted-bib>

Short rows

You work short rows along the edge.
Work double stitches according to the *German short rows* technique.
Pull the working yarn up and over the stitch on your left needle, pull to tighten and you have created a "double stitch" (2 stitches).
Slip this double stitch on to your right needle. Knit or purl the double stitch together in the next row.

Increases

Pick up the strand between 2 stitches with your left needle and knit through back loop.

Picot edge

At the end you work a crocheted picot edge along the outside edge of the bib.

Pattern

CO 58 stitches on circular needles size 3,5 mm / US 4 and two strands of yarn.

NB. The first stitch on every row is an edge stitch. Slip the first stitch knitwise on RS and purlwise on WS.

Purl one row.

Insert a marker in the 15th, 22nd, 29th, 30th, 37th and 44th stitch.

Increases and short rows

Row 1, RS: knit until 15th stitch, increase 1 stitch, knit until 22nd stitch, increase 1 stitch, knit until 29th stitch, increase 1 stitch (this is the middle of piece), knit the 30th stitch, increase 1 stitch, knit to and including the 37th stitch, increase 1 stitch, knit to and including the 44th stitch, increase 1 stitch, knit the rest of the row = 6 stitches increased.

Row 2, WS: Purl until 4 stitches are left on row, turn.

Row 3: Work one double stitch, *knit until increase, increase 1 stitch*, repeat a total of 3 times (this is the middle of the piece), *knit until increase, increase 1 stitch*, repeat a total of 3 times, knit until there are 4 stitches left on row, turn.

Row 4: Purl until there are 4 stitches left before previous turn (including the double stitches), turn.

Continue in this way, working short rows in all rows and increases in all RS rows until 12 stitches has been increased mid front. Continue working the stitches on your left needle and knit the double stitches together.

Work a buttonhole in the next row as follows:

Slip edge stitch purlwise, purl 2 stitches together, yarn over, purl the remaining stitches on row and purl double stitches together.

Knit one row.

Bind off all stitches in next WS row.

Break off one strand and pull it through the remaining stitch to tighten. Work the edge with the remaining strand.

Edge

Use your crochet hook 2,5 mm.

Picot edge

You work the picot edge as follows: ch3, 1 sc in first ch, 1 sc around edge of bib. Work one picot in every 3rd stitch. Finish with 1 sc.

Single crochet edge

Work 1 row of dc through back loop of stitch around the edge of the bib.

Enjoy!