

Pattern

Teddy Hooded jacket

Adult



Knitted with Teddy
- 100 % Polyester 50g/ 65 m
Ribbed edges in Cosy
- 60% Cotton/40% Acrylic 50g/ 100 m

YARN USAGE

Size	Teddy	Cosy
XS:	850 g	50 g
S:	900 g	50 g
M:	1050 g	50 g
L:	1100 g	50 g
XL:	1200 g	50 g
XXL:	1300 g	50 g
XXXL:	1400 g	50 g

MATERIALS

Buttons

Circular needles and
Double pointed needles:
3,0 and 3,5 mm

Gauge:

19 stitches x 33 rows
= 10 x 10 cm

Skill Level:

★★★★ of 5.

Go handmade
quality design in a unique style

www.gohandmade.net
© 2023

YARN USAGE

	Teddy	Cosy
XS:	850 g	50 g
S:	900 g	50 g
M:	1050 g	50 g
L:	1100 g	50 g
XL:	1200 g	50 g
XXL:	1300 g	50 g
XXXL:	1400 g	50 g

MATERIALS

Buttons 8 (8) 8 (8) 9 (9) 10

Stitch holder

Markers

Needles: 3,0 and 3,5 mm, 60 and 80 cm

Gauge: 19 stitches x 33 rows in stockinette stitch
on needle 3,5 mm = 10 x 10 cm

The given amounts of yarn are for guidance
only.

FINAL MEASUREMENTS

Size. XS (S) M (L) XL (XXL)

Chest **84 (88) 98 (108) 116 (126) 136** cm.

Length **57 (61) 65 (65) 65 (68) 70** cm.

Arm Length **42 (43) 44 (46) 48 (48) 48** cm.

DEFINITIONS

- Edge stitch The outermost stitch on each side is knitted.
- Increase Make an increase in the bar between the stitches, knit it as a knit stitch on the right side and as a purl stitch on the wrong side.
- Buttonhole Bind off 2 stitches, on the next row cast on 2 new stitches.
- (..) Indicates quantities for the 7 sizes.
- *...* What is stated in between is repeated throughout the round/row.

Teddy

Soft like a dream and a yarn many have been longing for, to be used for knitting and crocheting baby ware, teddies and blankets. Perfect for knitted teddy jackets and sweaters that are wonderful to wear. A "fluffy" yarn, that doesn't require any special techniques or stitches to get a nice and chunky result.

100% Polyester, 50 g/65 m.

Cosy

The thread is quite lightspun, soft and with a very special elasticity, which preserves the knit beautiful. The Cosy yarn is a bit vintage in its expression – warm, strong and even breathable.

60% Cotton/40% Acrylic, 50 g/100 m.

Go handmade
quality design in a unique style



GUIDE

- Knit across from sleeve to sleeve.
- Ribbing in Cosy - then stockinette stitch in Teddy.
- Stitches are picked up at the neckline for the hood.

NOTE: The numbers in the sections refer to the illustration on page 6.

TEDDY HOODED JACKET

XS (S) M (L) XL (XXL) XXXL

RIGHT SLEEVE

1. Cast on **49 (49) 53 (53) 55 (59) 59** stitches on a 3.0 mm (60 cm) needle in Cosy yarn and knit rib *knit 1, purl 1*, for a total of 5 rows. The first and last rows are the wrong side. On the last row, increase 1 stitch. There are a total of **50 (50) 54 (54) 56 (60) 60** stitches on the needle.

Switch to a 3.5 mm (60 cm) circular needle and Teddy yarn. Knit in stockinette stitch within the edge stitch on each side.

When the work measures **2 (2) 3 (3) 4 (3) 3** cm, increase 1 stitch on each side within the edge stitch. Repeat the increase every 2 cm a total of **18 (18) 19 (19) 19 (21)** times.

There are a total of **86 (86) 92 (92) 94 (102) 102** stitches on the needle.

Knit until the sleeve measures **42 (43) 44 (46) 48 (48) 48** cm, the last row being a wrong side row.

RIGHT FRONT AND BACK PIECE

2. Switch to a 3.5 mm (80 cm) circular needle.

Start the front and back pieces from the sleeve stitches.

Right side: Knit the sleeve stitches.

Cast on **66 (74) 78 (78) 79 (80) 83** stitches for the back piece.

Wrong side: Knit the back piece stitches and the sleeve stitches.

Cast on **66 (74) 78 (78) 79 (80) 83** stitches for the front piece.

There are a total of **218 (234) 248 (248) 252 (262) 268** stitches on the needle.

3. Place a marker in the middle of the work. Continue knitting across all stitches, with the edge stitch on the outer side. Knit until the work measures **12 (12) 14 (16) 17.5 (19.5) 22** cm from the marker.

The last row should be a wrong side row.

Knit **109 (117) 124 (124) 126 (131) 134** stitches and place them on a stitch holder. This is the front piece.

BACK PIECE

4. Divide the work for the front and back pieces at the neckline.

Continue with the remaining **109 (117) 124 (124) 126 (131) 134** stitches for the back piece. The outermost stitch on each side is the edge stitch. Bind off **1** stitch for the neckline, from the right side, at the beginning of the row. Knit the row.

Knit until the back piece measures **30 (32) 35 (38) 40.5 (43.5) 46** cm.

On the wrong side, at the end of the row, increase **1** stitch for the neckline. The last row ends at the neckline.

RIGHT FRONT PIECE

5. Set the stitches from the stitch holder onto a circular needle 3.5 mm (60 cm) and start at the top by the neckline on the wrong side.

Neckline: From the wrong side, bind off **1** stitch every **2nd** row, **14** times. There are a total of **95 (103) 110 (110) 112 (117) 120** stitches on the needle. Knit until the work measures **21 (22) 24.5 (27) 29 (31.5) 34** cm.

Buttonholes: Knit **8 (8) 8 (8) 9 (9) 10** buttonholes evenly distributed. The bottom buttonhole is placed about **2** cm from the edge. The top buttonhole is placed about **2** cm from the edge. The rest are evenly distributed in between.

When the front piece measures **23 (24) 26.5 (29) 31 (33.5) 36** cm, bind off all stitches from the right side.

LEFT FRONT PIECE

The left front piece is knitted separately, as a mirror image of the right front piece. It is then joined with the stitches from the back piece when it reaches the same size as the right front piece.

6. Cast on **95 (103) 110 (110) 112 (117) 120** stitches on a size 3.5 mm (60 cm) needle in Teddy yarn. Knit in stockinette stitch for the same number of rows as on the right front piece.

Neck: From the right side, increase **1** stitch on every **2nd** row, **14** times.

There are a total of **109 (117) 124 (124) 126 (131) 134** stitches on the needle.

LEFT FRONT AND BACK PIECE

7. Once the decreases are completed, knit the front piece together with the back piece, from the right side. There are a total of **218 (234) 248 (248) 252 (262) 268** stitches on the needle. Place a marker at the center of the work.
8. When the work measures **12 (12) 14 (16) 17.5 (19.5) 22** cm, bind off **66 (74) 78 (78) 79 (80) 83** stitches for the front piece from the right side, and complete the row. On the next row, from the wrong side, bind off **66 (74) 78 (78) 79 (80) 83** stitches for the back piece.

There are a total of **86 (86) 92 (92) 94 (102) 102** stitches remaining for the left sleeve. Place a marker at the center of the work.

LEFT SLEEVE

9. Knit until the work measures **6 (7) 5 (7) 8 (5) 5** cm, with the last row being from the wrong side. On the next row, from the right side, decrease 1 stitch on each side within the edge stitch.

Repeat the decrease every **2** cm a total of **18 (18) 19 (19) 19 (21)** times.

There are a total of **50 (50) 54 (54) 56 (60) 60** stitches on the needle.

Knit until the left sleeve measures the same as the right sleeve.

On the last row, from the right side, decrease 1 stitch. There are a total of **49 (49) 53 (53) 55 (59) 59** stitches on the needle.

Switch to a 3.0 mm (60 cm) circular needle and Cosy yarn. Knit **5** rows in rib pattern *knit 1, purl 1*.

Bind off in rib pattern.

HOOD

10. With a 3.5 mm (60 cm) circular needle and Teddy yarn, pick up stitches around the neckline. Start **3** cm in from the edge of the right front piece and finish **3** cm from the edge of the left front piece. Pick up **80 (84) 88 (92) 94 (100) 100** stitches in total. Knit in stockinette stitch back and forth, within the edge stitch on each side.

When the work measures **8** cm, evenly increase **14** stitches.

There are a total of **94 (98) 102 (106) 108 (114) 114** stitches on the needle.

Then, when the work measures **13** cm, evenly increase **14** stitches.


There are a total of **108 (112) 116 (120) 122 (128) 128** stitches on the needle.

When the work measures **27 (28) 29 (30) 31 (32) 33** cm, with the last row on the wrong side, divide the work in half.

Join the top of the hood together while simultaneously binding off as follows:

Hold both needles in the same hand with the wrong side facing outward. Knit the first stitch from both needles together, knit the second stitch from both needles together, then pass the first stitch over. Continue in the same manner across the row.

Front edge: From the right side, with a 3.0 mm (60 cm) circular needle and Cosy yarn, pick up stitches along the edge of the hood's front edge. Knit **5** rows in rib pattern *knit 1, purl 1*. Bind off in rib pattern.



Good to know

Needle Size + Tension

Knitters knit very differently: some knit with a needle size 2,0 mm and obtain the same size of design quality as a person who knits with a needle size 4,0 mm. We owe this knowledge to the team of knitters who join us.

The key to knit a specific size is a lot about the knitting style/hands/skills, rather than the size of needles.

Therefore, we will recommend a range of needle sizes.



LOT3 1082023

Go handmade
quality design in a unique style