

Pattern Sweater Robin - Adult



Knitted with Teddy
- 100 % Polyester 50g/ 65 m
Ribbed edges in Cosy
- 60% Cotton/40% Acrylic 50g/ 100 m



YARN USAGE		
Size.	Teddy	Cosy
XS:	700 g	50 g
S:	750 g	50 g
M:	800 g	50 g
L:	850 g	50 g
XL:	950 g	50 g
XXL:	1050 g	50 g
XXXL:	1150 g	50 g

MATERIALS
Zipper 35 cm
Circular Needles: 3,0 and 3,5 mm
Gauge:
19 stitch x 33 rows = 10 x 10 cm
Skill Level:
★★★★★ of 5



Light lavender
17375

Rose
17382

Grey
17317

Dark grey
17366

Brown
17318

Brown
17383

Petrol
17348

Marine blue
17652



YARN USAGE

	Teddy	Cosy
XS:	700 g	50 g
S:	750 g	50 g
M:	800 g	50 g
L:	850 g	50 g
XL:	950 g	50 g
XXL:	1050 g	50 g
XXXL	1150 g	50 g

MATERIALS

Zipper 35 cm

Marker

Stitch holder

Circular Needles: 3,0 mm and 3,5 mm
60 and 80 cm

Gauge: 19 stitch x 33 rows in Stockinette Stitch
on needle 3,5 mm = 10 x 10 cm

The given amounts of yarn are for guidance only

GUIDE:

- Knit in the round on a circular needle up to the armhole, where the work is divided.
- The outer side of the pocket is worked back and forth and is joined with the front piece.
- The sleeves are worked back and forth and then sewn in.

DEFINITIONS

- Decrease** At the beginning of the row; knit 2 stitches together through the back loop.
At the end of the row; knit 2 stitches together.
- Increase** Make an increase in the loop between the stitches, knit it on the right side and purl on the wrong side.
- (..) Indicates quantities for the 7 sizes
- *...* What is between is repeated throughout the row

FINAL MEASUREMENTS

Size. XS (S) M (L) XL (XXL) XXXL

Chest **90 (96) 108 (112) 122 (136) 146** cm.

Length **50 (52) 54 (56) 58 (60) 62** cm.

Arm Length **44 (45) 46 (47) 47 (48) 48** cm.

Teddy

Soft like a dream and a yarn many have been longing for, to be used for knitting and crocheting baby ware, teddies and blankets. Perfect for knitted teddy jackets and sweaters that are wonderful to wear. A "fluffy" yarn, that doesn't require any special techniques or stitches to get a nice and chunky result.

100% Polyester, 50 g/65 m.

Cosy

The thread is quite lightspun, soft and with a very special elasticity, which preserves the knit beautiful. The Cosy yarn is a bit vintage in its expression – warm, strong and even breathable.

60% Cotton/40% Acrylic, 50 g/100 m.

Go handmade
quality design in a unique style



ROBIN SWEATER

XS (S) M (L) XL (XXL) XXXL

BACK AND FRONTPIECE

Cast on **172 (184) 196 (212) 232 (260) 280** stitches on a 3.0 mm (80 cm) needle in Teddy yarn. Work in the round in rib, *knit 1, purl 1*.

Knit **3** rounds. Place a marker at the beginning of the round and place another marker after **86 (92) 98 (106) 116 (130) 140** stitches.

The first marker is the left side of the work. The second marker is the right side of the work.

Switch to a 3.5 mm (80 cm) needle. Continue knitting in stockinette stitch for the rest of the work. When the work measures **10** cm, start the pocket.

POCKET

Knit **19 (22) 24 (26) 28 (33) 37** stitches, place a marker, knit **48 (48) 50 (54) 60 (64) 66** stitches, place a marker, knit the rest of the round. The stitches between the markers are the pocket stitches.

Continue with the pocket. Work back and forth in stockinette stitch.

Knit back on the pocket stitches, from the wrong side. At the same time, cast on 1 new stitch on each side, these are edge stitches. There are a total of **50 (50) 52 (56) 62 (66) 68** stitches on the needle.

On the next row, from the right side, make **1** decrease within the edge stitch on each side. Repeat the decrease on every **2nd** row an additional **0 (0) 0 (0) 3 (2) 0** times. Then, on every **4th** row, decrease

9 (8) 10 (12) 10 (11) 13 times.

After that, on every **6th** row, decrease **1 (2) 1 (0) 0 (0) 0** times.

After the last decrease, from the right side, knit **5 (5) 5 (5) 5 (5) 5** rows in stockinette stitch.

On the last row, from the wrong side, bind off the edge stitch on both sides.

There are a total of **26 (26) 26 (28) 32 (36) 38** stitches on the needle.

Place the stitches on a stitch holder.

THE INNER SIDE OF THE POCKET

On the wrong side, pick up **48 (48) 50 (54) 60 (64)** stitches using a 3.5 mm needle for the inside of the pocket.

Pick up the stitches **7** cm down from the cast-on edge.

Knit **9** rows back and forth.

The inside of the pocket is knit together with the front and back pieces.

Knit the first **19 (22) 24 (26) 28 (33) 37** stitches of the front piece, knit **48 (48) 50 (54) 60 (64) 66** stitches from the inside of the pocket, knit the remaining stitches from the front piece, and then the stitches from the back piece.

Continue in stockinette stitch in the round until reaching the same measurement as the pocket.

On the next round, knit the front of the pocket together with the front piece.

Knit **30 (33) 36 (39) 42 (47)** stitches from the front piece. Place the pocket's **26 (26) 26 (28) 32 (36) 38** stitches on a 3.5 mm needle.

Hold the needle parallel to the circular needle and knit the pocket's outer side stitches together with the pocket's inner side stitches. Complete the round.

RIB EDGE ON THE POCKET

Right side: Begin from the top. Collect stitches evenly along the edge using a 3.0 mm needle and Cosy yarn. The total stitch count should be an odd number. Work ribbing by knitting one and purling one within the edge stitches on each side. Knit 3 rows. Bind off using the ribbing pattern.

Left side: Begin from the bottom. Pick up stitches as done on the right side. Work ribbing as on the right side.

The rib edges are sewn onto the front piece.



BACK AND FRONT PIECES - CONTINUED

Continue in stockinette stitch in the round.

Knit until the work measures **29.5 (30.5) 32.5 (33.5) 34.5 (36.5) 37.5** cm. Divide the work at the armhole.

Knit **86 (92) 98 (106) 116 (130) 140** stitches. Place them on a stitch holder, this is the front piece.

BACK PIECE

Continue with the remaining **86 (92) 98 (106) 116 (130) 140** stitches for the back piece.

Cast on **1** new stitch on each side, these are edge stitches.

There are a total of **88 (94) 100 (108) 118 (132) 142** stitches on the needle.

First row is the right side.

Knit in stockinette stitch back and forth.

Knit until the back piece measures **48.5 (50.5) 52.5 (54.5) 56.5 (58.5) 60.5** cm.

Neck and Shoulder:

On the right side, bind off **10 (11) 12 (13) 14 (16)** stitches at the beginning of the row for the right shoulder,

knit **22 (24) 26 (28) 31 (35) 38** stitches, bind off **24 (24) 24 (26) 28 (30) 32** stitches at the center for the neck, knit to the end of the row.

Each side is worked separately.

Left side:

Wrong side: Bind off **10 (11) 12 (13) 14 (16)** stitches for the shoulder, knit to the end of the row.

Right side: Bind off **2** stitches for the neckline, knit to the end of the row.

Wrong side: Bind off **10 (11) 12 (13) 14 (16)** stitches

for the shoulder, knit to the end of the row.
Right side: Knit to the end of the row.
Wrong side: Bind off the remaining **10 (11) 12 (13) 15 (17)** stitches for the shoulder.

Right side:

Wrong side: Knit across the row.
Right side: Bind off **10 (11) 12 (13) 14 (16)** stitches for the shoulder, knit across the row.
Wrong side: Bind off **2** stitches for the neck, knit across the row.
Right side: Bind off **10 (11) 12 (13) 15 (17)** stitches for the shoulder, knit across the row.

FRONT PIECE

Place the stitches from the front piece onto a 3.5 mm (60 cm) needle.

First row is the right side.

Cast on **1** new stitch on each side for the edge stitch.

There are a total of **88 (94) 100 (108) 118 (132) 142** stitches on the needle.

Work in stockinette stitch back and forth.

Neck Opening:

On the first row from the right side, bind off the **2** center stitches. Each side is worked separately. There are a total of **43 (46) 49 (53) 58 (65) 70** stitches on each side.

Right side:

When the work measures **43 (45) 47 (49) 51 (53) 55** cm, start the neck shaping.

Bind off from the right side every 2nd row for **7-2-2-1-1 (7-2-2-1-1) 7-2-2-1-1 (8-2-2-1-1) 8-2-2-2-1 (9-2-2-2-1) 10-2-2-2-1** stitches.

When the work measures **48.5 (50.5) 52.5 (54.5) 56.5 (58.5) 60.5** cm, start the shoulder bind-offs.

Bind off from the wrong side every 2nd row for **10-10 (11-11-11) 12-12-12 (13-13-13) 14-14-15 (16-16-17) 17-18-18** stitches.

Left side:

When the work measures **43 (45) 47 (49) 51 (53) 55** cm, start the neck bind-offs.

Bind off from the wrong side every 2nd row for **7-2-2-1-1 (7-2-2-1-1) 7-2-2-1-1 (8-2-2-1-1) 8-2-2-2-1 (9-2-2-2-1) 10-2-2-2-1** stitches.

When the work measures **48.5 (50.5) 52.5 (54.5) 56.5 (58.5) 60.5** cm, start the shoulder bind-offs. Bind off from the right side every 2nd row for **10-10 (11-11-11) 12-12-12 (13-13-13) 14-14-15 (16-16-17) 17-18-18** stitches.

Seam the shoulder seams together.

NECKLINE

Starting from the right side, use a 3.5 mm (60 cm) needle and Teddy yarn to pick up stitches evenly around the neckline.

Pick up **75 (77) 77 (81) 83 (87) 91** stitches.

Knit ribbing by alternating between knitting one stitch and purling one stitch within the edge stitch on each side.

Continue knitting for **7.5** cm, ending with a right side row.

Change to Cosy yarn and a 3.0 mm (60 cm) needle.

Knit **3** more rows of ribbing. Bind off using ribbing.

Left neck opening:

Using a 3.0 mm needle and Cosy yarn, pick up stitches evenly along the edge of the neckline.

Start on the right side at the top of the neckline.

Knit **1** row in purl.

Then, knit **5** rows in stockinette stitch.
Bind off in knit.

Right neck opening:

Start on the right side at the bottom of the neck opening.

Pick up stitches as done on the left side.

Knit the neck opening as on the left side.

Fold the edges in half towards the wrong side and secure them with small stitches.

SLEEVES X 2

Cast on **41 (41) 43 (43) 45 (45) 45** stitches using a 3.0 mm needle in Cosy yarn.

Work in rib pattern, alternating between knit and purl stitches, within the edge stitch on each side. The first and last row are on the wrong side.
Knit **3** rows.

Switch to a 3.5 mm needle and Teddy yarn.

Continue in stockinette stitch within the edge stitch on each side.

On the first row, increase **7** stitches evenly spaced.
There are a total of **48 (48) 50 (50) 52 (52) 52** stitches on the needle.

When the work measures **3** cm, start the increases.

XS: Increase **1** stitch inside the edge stitch on every **10th** row, **4** times.

Then, on every **12th** row, **6** times.

There are a total of **68** stitches on the needle.

S: Increase **1** stitch inside the edge stitch on every **10th** row, **12** times.

There are a total of **72** stitches on the needle.

M: Increase **1** stitch inside the edge stitch on every **10th** row, **8** times.

Then, on every **12th** row, increase **1** stitch inside the edge stitch, **3** times.

There are a total of **72** stitches on the needle.

L: Increase **1** stitch inside the edge stitch on every **10th** row, **12** times.

There are a total of **74** stitches on the needle.

XL: Increase **1** stitch inside the edge stitch on every **8th** row, **3** times.

Then, on every **10th** row, increase **1** stitch inside the edge stitch, **10** times.

There are a total of **78** stitches on the needle.

XXL: Increase **1** stitch inside the edge stitch on every **8th** row, **2** times.

Then, on every **10th** row, increase **1** stitch inside the edge stitch, **11** times.

There are a total of **78** stitches on the needle.

XXXL: Increase **1** stitch inside the edge stitch on every **8th** row, **11** times.

Then, on every **10th** row, increase **1** stitch inside the edge stitch, **4** times.

There are a total of **82** stitches on the needle.

When the work measures **44 (45) 46 (47) 47 (48)** cm, bind off from the right side.

ZIPPER

Zipper facing:

Cast on **12** stitches using a 3.5 mm needle in Cosy yarn.

The first row is the wrong side.

Knit in stockinette stitch.

The edge stitch is worked as follows: At the beginning of the row, lift the stitch with the yarn in front of the work; at the end of the row, knit the stitch.

Knit until the work measures **4** cm, with the last row on the wrong side. Divide the facing with **6** stitches for each side. Knit each side separately. Continue knitting the edge stitch as the edge.

Knit until the work matches the measurements of the neckline and the collar.

Bind off.

Sew in the zipper.

Attach the facing on the inside.



Good to know

Needle Size + Tension

Knitters knit very differently: some knit with a needle size 2,0 mm and obtain the same size of design quality as a person who knits with a needle size 4,0 mm. We owe this knowledge to the team of knitters who join us. The key to knit a specific size is a lot about the knitting style/hands/skills, rather than the size of needles. Therefore, we will recommend a range of needle sizes.



LOT24082023

Go handmade

quality design in a unique style