



**CROCHET PATTERN**

# Lights Up

## Top


**Design: Caroline Edal, Tarda Studio | Hobbii Design**

## MATERIALS

2 (3) 3 (3) skeins of Party Deluxe col Creme (18176)

Crochet hook 4 mm

## GYARN QUALITY

 **Party Deluxe**, Go Handmade  
100% Polyester  
50 g (1.75 oz) = 250 m (273 yds)

## GAUGE

10 x 10 cm (4" x 4")= 24 sts x 8 r

## ABBREVIATIONS

Dc = double crochet  
Ch = chain  
Sl st = slip stitch  
St(s) = stitch(es)  
\*..\* = repeat from \* to \* until end of round  
Beg = beginning  
Ch-sp = chain space

## SIZE

S (M) L (XL)

## MEASUREMENTS

Length: 28 (31) 34 (37) cm/11 (12.2) 13.4 (14.6) inches  
Width (from sleeve to sleeve):146,5 (156,5) 166,5 (176,5) cm/57.7 (61.6) 65.6 (69.5) inches

## PATTERN INFORMATION

The Lights Up Top brings party and good spirits to your outfit. Wear it over your everyday clothes, or style it with your party gown to sparkle like a star.

## HASHTAGS FOR SOCIAL MEDIA

#hobbilightsup  
#hobbiidesign

## BUY THE YARN HERE

<https://shop.hobbii.com/lights-up-top>



## QUESTIONS

If you have any questions regarding this pattern, please feel free to email us at [support@hobbii.com](mailto:support@hobbii.com)

Please make sure to include the pattern's name and number.

Happy Crafting!

# Pattern



## TIPS AND INFO

The Lights Up Top starts at "SLEEVE 1", after which "FRONT PANEL" and "BACK PANEL" are worked from there. From these you will start "SLEEVE 2" and cut the yarn. The "WAIST PANEL" on the other hand is worked separately and placed between "FRONT PANEL" and "BACK PANEL" creating the unique twist at the front.

## Sleeve 1

Round 1: Ch 68 (76) 84 (92). Sl st in first ch to create a circle.

Round 2: Ch 4, \*Skip 1 st, 1 dc, ch 1 (i.e., 1 dc in every 2. st in the circle). \* sl st in 3. ch from beg of round. You have now made 34 (38) 42 (46) ch-sps.

Repeat "Round 2" until you have a total of 46 (48) 50 (52) rounds and the panel measures approx. 57,5 (60) 62,5 (65) cm/22.6 (23.6) 24.6 (25.6) inches, or desired length.

## FRONT PANEL

Row 1: Ch 3 (Note! This is the upper part of the top, which will later form the neckline), \*ch 1, skip 1 st, 1 dc (i.e., 1 dc in every 2. st in the circle) \*x15 (17) 19 (21). You have now made 15 (17) 19 (21) ch-sps. (NOTE! the 15. (17.) 19. (21.) ch-sp is the lower part of the top).

Row 2: Turn your work to crochet back across the sts of "row 1". Ch 3, \*ch 1, skip 1 st, 1 dc (i.e., 1 dc in every 2. st in the circle) \*x15 (17) 19 (21). You have now made another 15 (17) 19 (21) ch-sps.

Repeat "Row 2" until you have a total of 30 (34) 38 (42) rows and the panel measures approx. 37,5 (42,5) 47,5 (52,5) cm/14.8 (16.7) 18.7 (20.7) inches, or desired length. It is important to create 15 (17) 19 (21) ch-sps on each row.

Finish "FRONT PANEL" by cutting the yarn, pull yarn through st and pull tight.

## BACK PANEL

Row 1: Start in the same st as for the front panel (Note! This is the upper part of the top, which will later form the neckline). Turn work straight away to work in the opposite direction of the front panel. Ch 3, \*ch 1, skip 1 st, 1 dc (i.e., 1 dc in every 2. st in the circle) \*x 6 (8) 10 (12). You have now made 6 (8) 10 (12) ch-sps.

Row 2: Turn your work to crochet back across the sts of "row 1". Ch 3, \*ch 1, skip 1 st, 1 dc (i.e., 1 dc in every 2. st in the circle) \*X6 (8) 10 (12). You have now made another 6 (8) 10 (12) ch-sps.

Repeat "row 2" until you have a total of 25 (29) 33 (37) rows and the panel measures approx. 31,5 (36,5) 41,5 (46,5) cm/12.4 (14.3) 16.3 (18.3) inches, or desired length. It is important to create 6 (8) 10 (12) ch-sps on each row, meaning the back panel is not as wide the front panel.

## SLEEVE 2

Ch 26 and join with a sl st to the lower part of the "FRONT PANEL", i.e., the 15. (17.) 19. (21.) ch-sp of the front panel (NOTE! If necessary read the section "FRONT PANEL" again to avoid any doubt about the upper and lower part of the top.

Round 1: Ch 4, \*Skip 1 st, 1 dc, ch 1 (i.e., 1 dc in every 2. st in the circle). \* sl st in 3. ch from beg of round to join. You have now made 34 (38) 42 (46) ch-sps across "FRONT PANEL", "BACK PANEL" and the ch-26.

Repeat "Round 1" until you have a total of 46 (48) 50 (52) rounds and the panel measures approx. 57,5 (60) 62,5 (65) cm/22.6 (23.6) 24.6 (25.6) inches, or desired length.

Finish "SLEEVE 2" by cutting the yarn, pull yarn through st and pull tight.

## WAIST PANEL

Row 1: ch 36 (40) 44 (48).

Row 2: ch 4, \*Skip 1 st, 1 dc, ch 1 (i.e., 1 dc in every 2. st). \* You have now made 18 (20) 22 (24) ch-sps.

Row 3: Turn your work to crochet back across the sts of "row 2". Repeat "Row 2" until you have a total of 72 (78) 84 (90) rows and the panel measures approx. 90 (97,5) 105 (112,5) cm/35.4 (38.4) 41.3 (44.3), or desired length

Place work between "FRONT PANEL" and "BACK PANEL".

Now join work to row 1 by working a sl st into the front loop of the 1. st of row 1 and the front loop of the 1. st of the last row at the same time. Then continue to work 1 sl st in the front loop of the 2. st of row 1 and the front loop of the 2. st of the last row. Then in the 3. St and so on. Repeat until all sts have been slip stitched together.

Finish "WAIST PANEL" by cutting the yarn, weave yarn through st, pull tight.

Place the slip stitch join in the middle of the “FRONT PANEL” to hide the seam itself behind the twisted front.

Weave in ends.

**Enjoy!**

Caroline Edal, Tarda Studio

