

Pattern

Teddy Hooded jacket

- Little One's & Tweens



Many colors

Knitted with Teddy
- 100 % Polyester 50g/ 65 m
Ribbed edges in Cosy
- 60% Cotton/40% Acrylic 50g/ 100 m



YARN USAGE

Size	Teddy	Cosy
1-2 yrs:	350 g	50 g
3-4 yrs:	450 g	50 g
5-6 yrs:	500 g	50 g
7-8 yrs:	550 g	50 g
9-10 yrs:	650 g	50 g
11-12 yrs:	700 g	50 g

MATERIALS

Buttons

Circular needles and

Double pointed
needles:

3,0 and 3,5 mm

Gauge Teddy:

19 stitches x 33 rows
= 10 x 10 cm

Skill Level:

★★★★ of 5.

Go handmade

quality design in a unique style

www.gohandmade.net
© 2023

YARN USAGE

	Teddy	Cosy
1-2 yrs:	350 g	50 g
3-4 yrs:	450 g	50 g
5-6 yrs:	500 g	50 g
7-8 yrs:	550 g	50 g
9-10 yrs:	650 g	50 g
11-12 yrs:	700 g	50 g

MATERIALS

Buttons 5 (6) 6 (7) 7 (7)

Stitch holder

Markers

Needles: 3,0 og 3,5 mm, 60 og 80 cm

Gauge Teddy:

19 stitches x 33 rows in stockinette stitch on
needle 3,5 mm = 10 x 10 cm

The given amounts of yarn are for guidance only.

FINAL MEASUREMENTS

Str. 1-2 (3-4) 5-6 (7-8) 9-10 (11-12) Years

Chest **57 (64) 68 (74) 76 (80)** cm.

Length **34 (38) 42 (46) 50 (52)** cm.

Arm Length **25 (27) 32 (34) 36 (40)** cm.

DEFINITIONS

- Edge stitch The outermost stitch on each side is knitted.
- Increase Make an increase in the bar between the stitches, knit it as a knit stitch on the right side and as a purl stitch on the wrong side.
- Buttonhole Bind off 2 stitches, on the next row cast on 2 new stitches.
- (..) Indicates quantities for the 7 sizes.
- *...* What is stated in between is repeated throughout the round/row.

Teddy

Soft like a dream and a yarn many have been longing for, to be used for knitting and crocheting baby ware, teddies and blankets. Perfect for knitted teddy jackets and sweaters that are wonderful to wear. A "fluffy" yarn, that doesn't require any special techniques or stitches to get a nice and chunky result.

100% Polyester, 50 g/65 m.

Cosy

The thread is quite lightspun, soft and with a very special elasticity, which preserves the knit beautiful. The Cosy yarn is a bit vintage in its expression – warm, strong and even breathable.

60% Cotton/40% Acrylic, 50 g/100 m.

Go handmade
quality design in a unique style



GUIDE

- Knit across from sleeve to sleeve.
- Ribbing in Cosy - then stockinette stitch in Teddy.
- Stitches are picked up at the neckline for the hood.

NOTE: The numbers in the sections refer to the illustration on page 6.

TEDDY HOODED JACKET

1-2 (3-4) 5-6 (7-8) 9-10 (11-12) Years

RIGHT SLEEVE

1. Cast on **33 (35) 37 (39) 41 (43)** stitches on needle 3.0 mm (60 cm) in Cosy yarn and knit rib *1 knit, 1 purl* for a total of **3 (3) 3 (3) 5 (5)** rows. The first and last row are the purl side. On the last row, increase **1** stitch. There are a total of **34 (36) 38 (40) 42 (44)** stitches on the needle.

Switch to circular needle 3.5 mm (60 cm) and Teddy yarn. Knit stockinette stitch within the edge stitch, on each side.

When the work measures **2** cm, increase **1** stitch on each side, within the edge stitch. Repeat increases every **2** cm a total of **6 (8) 6 (7) 8 (8)** times. Then, repeat increases every **3** cm a total of **4 (3) 6 (6) 6 (7)** times.

There are a total of **54 (58) 62 (66) 70 (74)** stitches on the needle.

Knit until the sleeve measures **25 (27) 32 (34) 36 (40)** cm, with the last row on the purl side.

RIGHT FRONT AND BACK PIECE

2. Switch to circular needle 3.5 mm (80 cm).

Start the front and back pieces from the stitches of the sleeves.

Right side: Knit the stitches of the sleeves.

Cast on **38 (44) 49 (55) 61 (63)** stitches for the back piece.

Wrong side: Knit the stitches of the back piece and the sleeves.

Cast on **38 (44) 49 (55) 61 (63)** stitches for the front piece.

There are a total of **130 (146) 168 (176) 192 (200)** stitches on the needle.

3. Place a marker in the middle of the work. Continue knitting across all stitches, with the edge stitch being the outermost stitch. Knit until the work from the marker measures **9 (10) 11 (12) 12 (12.5)** cm. The last row is from the purl side.

Knit **65 (73) 80 (88) 96 (100)** stitches, place them on a stitch holder, this is the front piece.

BACK PIECE

4. Divide the work at the neckline for the front and back pieces.

Continue with the remaining **65 (73) 80 (88) 96 (100)** stitches for the back piece. The edge stitch on each side remains as the edge stitch.

From the right side, bind off **1** stitch for the neckline at the beginning of the row. Complete the row.

Knit until the back piece measures **19 (22) 23 (24) 28 (29.5)** cm.

From the purl side, increase **1** stitch for the neckline at the end of the row. The last row ends at the neckline.

RIGHT FRONT PIECE

5. Place the stitches from the stitch holder onto a circular needle 3.5 mm (60 cm). Start at the top by the neckline, on the purl side.

Neck: From the purl side, bind off **1** stitch every **2** rows, **6 (7) 8 (8) 9 (10)** times.

There are a total of **59 (66) 72 (80) 87 (90)** stitches.

Knit until the work measures **15.5 (17.5) 18.5 (19.5) 20 (21)** cm.

Buttonholes: Knit **5 (6) 6 (7) 7 (7)** buttonholes evenly spaced.

The bottom buttonhole is placed approximately **2** cm from the edge.

The top buttonhole is placed approximately **2** cm from the edge.

Distribute the remaining buttonholes evenly in between.

When the front piece measures **17 (19) 20 (21.5) 22 (23)** cm, bind off all stitches from the right side.

LEFT FRONT PIECE

The left front piece is knitted separately, as a mirror image of the right front piece. It is then joined with the stitches from the back piece when it reaches the same size as the right front piece.

6. Cast on **59 (66) 72 (80) 87 (90)** stitches on size 3.5 mm (60 cm) needles using Teddy yarn. Knit stockinette stitch for the same number of rows as indicated on the right front piece.

Neck: From the right side, increase **1** stitch every **2** rows, **6 (7) 8 (8) 9 (10)** times.

There are a total of **65 (73) 80 (88) 96 (100)** stitches on the needle.

LEFT FRONT AND BACK PIECE

7. Once the increases are completed, knit the front piece together with the back piece from the right side.

There are a total of **130 (146) 168 (176) 192 (200)** stitches on the needle.

Place a marker in the middle of the work..

8. When the work measures **9 (10) 11 (12) 12 (12.5)** cm, bind off the front piece's **38 (44) 49 (55) 61 (63)** stitches from the right side, and knit the row. On the next row, from the purl side, bind off the back piece's **38 (44) 49 (55) 61 (63)** stitches.

There are a total of **54 (58) 62 (66) 70 (74)** stitches remaining for the left sleeve.

Place a marker in the middle of the work.

LEFT SLEEVE

9. Knit until the work measures **1 (2) 2 (2) 2 (3)** cm, with the last row on the purl side.

On the next row, from the right side, decrease **1** stitch on each side within the edge stitch.

Repeat the decreases every **3** cm a total of **4 (3) 6 (6) (6) 7** times.

Then, repeat the decreases every **2** cm a total of **6 (8) 6 (7) 8 (8)** times.

There are a total of **34 (36) 38 (40) 42 (44)** stitches on the needle.

Knit until the left sleeve measures the same as the right sleeve.

On the last row from the right side, decrease **1** stitch.

There are a total of **33 (35) 37 (39) 41 (43)** stitches on the needle.

Switch to circular needle 3.0 mm (60 cm) and Cosy yarn.

Knit **3 (3) 3 (3) 5 (5)** rows of rib *1 knit, 1 purl*.
Bind off in rib.

HOOD

10. Using a circular needle 3.5 mm (60 cm) and Teddy yarn, pick up stitches around the neckline. Start **2 (2) 2 (2) 3 (3)** cm in from the right front edge and end **2 (2) 2 (2) 3 (3)** cm from the left front edge. Pick up **50 (52) 56 (60) 64 (68)** stitches.

Knit stockinette stitch back and forth within the edge stitch on each side.

When the work measures **6** cm, increase **13** stitches evenly spaced.

There are a total of **63 (65) 69 (73) 77 (81)** stitches on the needle.

Then, when the work measures **9 (10) 11 (11.5) 12 (12.5)** cm, increase **13** stitches evenly spaced.

There are a total of **76 (78) 82 (86) 90 (94)** stitches on the needle.


When the work measures **21 (22) 22 (23) 24 (25)** cm, with the last row on the purl side, divide the work in the middle.

Knit the hood together at the top while simultaneously binding off as follows:

Hold both needles in the same hand with the wrong side facing out. Knit the first stitch from each needle together, then knit the second stitch from each needle together and pass the first stitch over. Continue in this manner across the row.

Front Edge: From the right side, using a circular needle 3.0 mm (60 cm) and Cosy yarn, pick up stitches along the hood's front edge.

Knit **3 (3) 3 (3) 5 (5)** rows of rib *1 knit, 1 purl*.
Bind off in rib.



Good to know

Needle Size + Tension

Knitters knit very differently: some knit with a needle size 2,0 mm and obtain the same size of design quality as a person who knits with a needle size 4,0 mm. We owe this knowledge to the team of knitters who join us.

The key to knit a specific size is a lot about the knitting style/hands/skills, rather than the size of needles.

Therefore, we will recommend a range of needle sizes.



LOT3 1082023

Go handmade

quality design in a unique style