

# Pattern

## Sweater Robin

### - Little One's & Tweens



Knitted with Teddy  
- 100% Polyester, 50 g/65 m.  
Ribbed edges in Cosy  
- 60% Cotton/40% Acrylic, 50 g/100 m.

#### YARN USAGE

Size	Teddy	Cosy
3-4 yrs:	350 g	50 g
5-6 yrs:	450 g	50 g
7-8 yrs:	500 g	50 g
9-10 yrs:	600 g	50 g
11-12 yrs:	650 g	50 g

#### MATERIALS

Zipper 35 cm  
Circular Needles:  
3,0 and 3,5 mm  
Gauge:  
19 stitch x 33 rows  
= 10 x 10 cm  
Skill Level:  
★★★★ of 5

Go handmade

quality design in a unique style

www.gohandmade.net  
© 2023



Light lavender  
17375

Rose  
17382

Grey  
17317

Dark grey  
17366

Brown  
17318

Brown  
17383

Petrol  
17348

Marine blue  
17652



## YARN USAGE

	<b>Teddy</b>	<b>Cosy</b>
3-4 year:	350 g	50 g
5-6 year:	450 g	50 g
7-8 year:	500 g	50 g
9-10 year:	600 g	50 g
11-12 year:	650 g	50 g

## MATERIALS

Zipper 35 cm

Marker

Stitch holder

Circular Needles: 3,0 mm and 3,5 mm  
60 and 80 cm

Gauge: 19 stitch x 33 rows in Stockinette Stitch  
on needle 3,5 mm = 10 x 10 cm

The given amounts of yarn are for guidance only

## FINAL MEASUREMENTS

<b>Size. 3-4 yrs (5-6 yrs) 7-8 yrs (9-10 yrs) 11-12 yrs</b>	
Chest	<b>63 (65) 72 (78) 84</b> cm.
Length	<b>37 (42) 45 (48) 50</b> cm.
Arm Length	<b>23 (28) 32 (36) 39</b> cm.

## GUIDE:

- Knit in the round on a circular needle up to the armhole, where the work is divided.
- The outer side of the pocket is worked back and forth and is joined with the front piece.
- The sleeves are worked back and forth and then sewn in.

## DEFINITIONS

- Decrease** At the beginning of the row; knit 2 stitches together through the back loop.  
At the end of the row; knit 2 stitches together.
- Increase** Make an increase in the loop between the stitches, knit it on the right side and purl on the wrong side.
- (..) Indicates quantities for the 7 sizes
- \*...\* What is between is repeated throughout the row.

## Teddy

Soft like a dream and a yarn many have been longing for, to be used for knitting and crocheting baby ware, teddies and blankets. Perfect for knitted teddy jackets and sweaters that are wonderful to wear. A "fluffy" yarn, that doesn't require any special techniques or stitches to get a nice and chunky result.

100% Polyester, 50 g/65 m.

## Cosy

The thread is quite lightspun, soft and with a very special elasticity, which preserves the knit beautiful. The Cosy yarn is a bit vintage in its expression – warm, strong and even breathable.

60% Cotton/40% Acrylic, 50 g/100 m.

Go handmade  
quality design in a unique style



## ROBIN SWEATER

3-4 yrs (5-6 yrs) 7-8 yrs (9-10 yrs) 11-12 yrs

### BACK AND FRONTPIECE

Cast on **120 (124) 136 (148) 160** stitches on a 3.0 mm (60 or 80 cm) needle in Teddy yarn.

Knit in the round in rib, \*1 knit, 1 purl\*.

Knit **3** rounds.

Place a marker at the beginning of the round and another marker after **60 (62) 68 (74) 80** stitches.

The first marker is the left side and the start of the round. The second marker is the right side of the work.

Switch to a 3.5 mm (60 or 80 cm) needle.

Continue in stockinette stitch for the rest of the work. When the work measures **5.5 (6.5) 6.5 (7.5) 8.5** cm, start the pocket.

### POCKET

Knit **12 (12) 13 (15) 17** stitches, place a marker, knit **36 (38) 42 (44) 46** stitches, place a marker, knit the rest of the round.

The stitches between the markers are for the pocket.

*Continue with the pocket.*

*Knit back on the pocket stitches from the wrong side.*

Simultaneously, cast on **1** new stitch on each side, these are edge stitches.

There are a total of **38 (40) 44 (46) 48** stitches on the needle.

On the next row, from the right side, make **1** decrease within the edge stitch on each side.

Repeat this decrease every **2** rows for **3 (3) 4 (1) 3** more times.

Then, on every **4th** row, decrease **5 (6) 6 (9) 8** times. After the last decrease from the right side, knit **3** rows in stockinette stitch.

On the last row from the wrong side, bind off the edge stitches on both sides.

There are a total of **18 (18) 20 (22) 22** stitches left on the needle.

*Place the stitches on a stitch holder.*

### THE INNER SIDE OF THE POCKET

On the wrong side, pick up **36 (38) 42 (44) 46** stitches using a 3.5 mm needle for the inside of the pocket.

Pick up the stitches **4.5 (5.5) 5.5 (6.5) 7.5** cm up from the cast-on edge.

Knit **3** rows back and forth.

*Continue by knitting the pocket's inner side together with the front and back pieces.*

Knit the first **12 (12) 13 (15) 17** stitches of the front piece, knit **36 (38) 42 (44) 46** stitches from the pocket's inner side, knit the remaining stitches from the front piece, then the stitches from the back piece. Continue in the round in stockinette stitch until reaching the same length as the pocket.

*On the next round, knit the front of the pocket together with the front piece.*

Knit **21 (22) 24 (26) 29** stitches from the front piece. Place the pocket's **18 (18) 20 (22) 22** stitches on a 3.5 mm needle.

Hold the needle parallel to the circular needle and knit the pocket's outer side stitches together with the pocket's inner side stitches.

Knit the round.

## RIB EDGE ON THE POCKET

**Right side:** Start from the top.

Pick up stitches evenly along the edge with a size 3.0 mm needle and Cosy yarn.

The number of stitches should be odd.

Knit ribbing \*1 knit, 1 purl\* within the edge stitch on each side.

Knit **3** rows.

Bind off in rib.

**Left side:** Start from the bottom.

Pick up stitches as done on the right side.

Knit ribbing as on the right side.

*Sew the ribbed edges onto the front piece.*

## BACK AND FRONT PIECES - CONTINUED

Continue in stocking stitch.

Knit until the work measures **20 (24) 26 (29) 30** cm.

Divide the work at the armhole.

Knit **60 (62) 68 (74) 80** stitches.

Place them on a stitch holder, it's the front piece.

## BACK PIECE

Continue with the remaining **60 (62) 68 (74) 80** stitches for the back piece.

Cast on **1** new stitch on each side, these are edge stitches.

There are a total of **62 (64) 70 (76) 82** stitches on the needle.

The first row is the right side.

Knit in stocking stitch back and forth.

Knit until the back piece measures **36 (41) 44 (47) 49** cm.

**Neck and shoulder:**

On the right side, cast off **9 (10) 11 (12) 14** stitches

at the beginning of the row for the right shoulder, knit **12 (12) 13 (15) 16** stitches, cast off **20 (20) 22 (22) 22** stitches in the center for the neck, knit to the end of the row. Each side is worked separately.

**Left side:**

Wrong side: Cast off **9 (10) 11 (12) 14** stitches for the shoulder, knit to the end of the row.

Right side: Cast off **2** stitches for the neck, knit to the end of the row.

Wrong side: Cast off the remaining **10 (10) 11 (13) 14** stitches for the shoulder.

**Right side:**

Wrong side: Cast off **2** stitches for the neck, knit to the end of the row.

Right side: Cast off the remaining **10 (10) 11 (13) 14** stitches for the shoulder.

## FRONT PIECE

Place the stitches from the front piece onto a size 3.5 mm (60 cm) circular needle.

The first row is the right side.

Cast on **1** new stitch on each side for the edge stitches.

There are a total of **62 (64) 70 (76) 82** stitches on the needle.

Knit in stocking stitch back and forth.

**Neck Opening:**

On the first row from the right side, cast off the **2** center stitches.

Each side is worked separately.

There are a total of **30 (31) 34 (37) 40** stitches on each side.

**Right Side:**

When the work measures **31 (36) 39 (41) 43** cm, begin neck decreases.

Cast off on every **2nd** row from the right side for **6-2-1-1-1 (6-2-1-1-1) 6-2-2-1-1 (6-2-1-1-1-1) 6-2-1-**

**1-1-1** stitches.

When the work measures **37 (41) 44 (48) 52** cm, begin shoulder decreases.

Cast off on every **2nd** row from the wrong side for **9-10 (10-10) 11-11 (12-13) 14-14** stitches.

#### **Left Side:**

When the work measures **31 (36) 39 (41) 43** cm, begin neck decreases.

Cast off on every **2nd** row from the wrong side for **6-2-1-1-1 (6-2-1-1-1) 6-2-2-1-1 (6-2-1-1-1-1) 6-2-1-1-1-1** stitches.

When the work measures **37 (41) 44 (48) 52** cm, begin shoulder decreases.

Cast off on every **2nd** row from the right side for **9-10 (10-10) 11-11 (12-13) 14-14** stitches.

### **NECKLINE**

From the right side, using a size 3.5 mm (60 cm) needle and Teddy yarn, pick up stitches evenly around the neck.

Pick up **65 (65) 65 (71) 71** stitches.

Knit rib \*1 knit, 1 purl\* within the edge stitch on each side.

Knit **6 (6.5) 6.5 (7) 7** cm, with the last row being on the right side.

Switch to Cosy yarn and a size 3.0 mm (60 cm) needle.

Knit an additional **3** rows of rib. Cast off in rib.

#### **Left Neck Opening:**

With a size 3.0 mm needle and Cosy yarn, pick up stitches evenly along the edge of the neck opening.

Start on the right side at the top of the neck.

Knit **1** row purl.

Then knit **5** rows in stocking stitch.

Cast off in purl.

#### **Right Neck Opening:**

Start on the right side at the bottom of the neck.

Pick up stitches as done on the left side.

Knit the neck opening as on the left side.

*Fold the edges inwards and sew them securely with small stitches on the wrong side.*

### **SLEEVES X 2**

Cast on **35 (37) 37 (37) 39** stitches with a size 3.0 mm needle in Cosy. Knit ribbing \*1 knit, 1 purl\* within the edge stitches on each side. The first and last rows are purl. Knit **3** rows.

Switch to a size 3.5 mm needle and Teddy yarn. Continue in stockinette stitch within the edge stitches on each side.

On the first row, evenly increase **3 (3) 3 (5) 5** stitches.

There are a total of **38 (40) 40 (42) 44** stitches on the needle.

When the work measures **2** cm, start the increases.

For ages **3-4** years: Increase **1** stitch within the edge stitches on every **4th** row, **2** times.

Then, increase on every **6th** row, **9** times.

There are a total of **60** stitches on the needle.

For ages **5-6** years: Increase **1** stitch within the edge stitches on every **6th** row, **7** times.

Then, increase on every **8th** row, **5** times.

There are a total of **64** stitches on the needle.

For ages **7-8** years: Increase **1** stitch within the edge stitches on every **6th** row, **6** times.

Then, increase on every **8th** row, **7** times.

There are a total of **66** stitches on the needle.

For ages **9-10** years: Increase **1** stitch within the edge stitches on every **6th** row, **4** times.

Then, increase on every **8th** row, **10** times.  
There are a total of **70** stitches on the needle.

For ages **11-12** years: Increase **1** stitch within the edge stitches on every **6th** row, **5** times.  
Then, increase on every **8th** row, **10** times.  
There are a total of **74** stitches on the needle.

When the work measures **23 (28) 32 (36) 39** cm, bind off from the right side.

## ZIPPER

### Zipper facing:

Cast on **12** stitches with *Cosy* on a size 3.5 mm needle.

The first row is the wrong side.

Knit in stocking stitch.

The outermost stitch is the edge stitch and is worked as follows: At the beginning of the row, slip the stitch with the yarn in front of the work; at the end, knit the stitch.

When the work measures **4** cm, on the last row from the wrong side, divide the facing with **6** stitches on each side.

Knit each side separately.

Continue knitting the outermost stitch as an edge stitch.

Knit until the work matches the measurements of the neck opening and collar.

Bind off.

*Sew in the zipper.*


*Secure the facing on the inside.*



# Good to know

## Needle Size + Tension

Knitters knit very differently: some knit with a needle size 2,0 mm and obtain the same size of design quality as a person who knits with a needle size 4,0 mm. We owe this knowledge to the team of knitters who join us. The key to knit a specific size is a lot about the knitting style/hands/skills, rather than the size of needles. Therefore, we will recommend a range of needle sizes.



LOT24082023

# Go handmade

quality design in a unique style